

## How to apply ViCANdroid license on Kvaser device

Document Type	Guidelines
Document Classification	Public
Product	ViCANdroid
Department	R&D
Version	1.2

## Table of Contents

Revision History	2
Before asking license	2
Apply license	3
Legal Information	3
About this document	3
Trademarks	3
References	3


## Revision History

Date	Revision	Author	Description
20.09.2018	1.0	HL	Initial draft
20.09.2018	1.1	HL	Added how to apply the license
02.05.2019	1.2	HL	Updated logo

## Before asking license

When asking for a ViCANDroid license, user needs to provide below information of the Kvaser device.

1. Have Kvaser driver installed on your PC
2. Plug in your kvaser device to your PC
3. Open Kvaser Device Guide
4. Select View->Detailed information from the menu
5. Click on any channel of the Kvaser device, for example:



6. Send the screenshot to Zuragon for ViCANdroid license or send the **Device EAN number**, **serial number** and the **Drivername** to Zuragon via info@zuragon.com.
7. Zuragon will send you a license file.

## Apply license

Follow below procedure to apply the license to your Kvaser device.

1. Plug in your Kvaser device to your PC
2. Open Kvaser Device Guide
3. Open Tools->Customer Data from the menu
4. Select the Kvaser device you want to apply the license
5. Click "Write data..." button on the bottom right corner.
6. Copy the content of the license file and paste to the new window and click OK.

## Legal Information

### About this document

This document may not be reproduced without our prior written permission.

We believe that the information in this user guide was accurate at the time of printing. Zuragon cannot, however, assume responsibility for any errors or omissions in this document. The information in this document is subject to change without notice and should not be taken as a commitment by Zuragon.

### Trademarks

All product names mentioned in this manual are registered or unregistered trademarks of their respective owners.

## References